

Ubuntu - “do-release-upgrade” je usrao Apache

written by js | 2022-08-21

tl;dr rješenje

```
a2dismod php7.4
systemctl stop apache2
systemctl start apache2
a2dismod php8.1
systemctl stop apache2
systemctl start apache2
```

Trkeljačina

Nakon nadogradnje Ubuntuta na najnoviju novu verziju, OS se probudio usranoga Apache servera, ako ne i drugih stvari, ali zadržimo se sada na ovome. Naredba:

```
apache2ctl -M
```

kaže:

```
apache2:
Syntax error on line 146 of /etc/apache2/apache2.conf:
Syntax error on line 3 of /etc/apache2/mods-enabled/php7.4.load:
Cannot load /usr/lib/apache2/modules/libphp7.4.so into server:
/usr/lib/apache2/modules/libphp7.4.so:
cannot open shared object file:
No such file or directory
```

Gle, fakat:

```
ls -la /usr/lib/apache2/modules/libphp*
```

kaže da je tamo samo v.8.1, a nema 7.4

```
/usr/lib/apache2/modules/libphp8.1.so
```

Slično kaže i

```
journalctl -xeu apache2.service
```

...

Znači, upgrade je apgrejdao PHP, ali ne i konfiguraciju. Ta, pogledajmo onda redak 146 u “/etc/apache2/apache2.conf” (kod tebe može biti neki drugi red, naravno). Kaže:

```
IncludeOptional mods-enabled/*.load
```

što upućuje na drugu datoteku na koju ukazuje error, a to je “/etc/apache2/mods-enabled/php7.4.load”.

Rješenje

Onemogući PHP74, omogući PHP81. Vidi tl;dr

xphpx xapachex xapache2x xdoreleaseupgradex xfuckeryx xfuckupx
doreleaseupgrade fuckery fuckup