

# Ubuntu jebeno ide u sleep svakih X minuta

written by js | 2023-10-22

..a /var/log/syslog ti se pojavljuje ovo govno "non-stop":

```
Oct 22 14:16:41 <%ComputerName%> systemd[1]: Reached target Sleep.
Oct 22 14:16:41 <%ComputerName%> systemd[1]: Starting Record successful boot for GRUB...
Oct 22 14:16:41 <%ComputerName%> systemd[1]: Starting System Suspend...
Oct 22 14:16:41 <%ComputerName%> systemd-sleep[9599]: Entering sleep state 'suspend'...
Oct 22 14:16:41 <%ComputerName%> kernel: [ 4447.706687] PM: suspend entry (deep)
Oct 22 14:16:41 <%ComputerName%> systemd[1]: grub-common.service: Deactivated successfully.
Oct 22 14:16:41 <%ComputerName%> systemd[1]: Finished Record successful boot for GRUB.
Oct 22 14:16:41 <%ComputerName%> systemd[1]: Starting GRUB failed boot detection...
```

## Rješenje? Možda, nekome..

```
sudo nano /etc/default/grub
```

i umjesto

```
GRUB_CMDLINE_LINUX_DEFAULT="quiet splash"
```

stavi

```
GRUB_CMDLINE_LINUX_DEFAULT="quiet splash acpi=off apm=off"
```

```
pa update-grub i sudo reboot now
```

# Možda ovo

```
sudo systemctl mask sleep.target suspend.target  
hibernate.target hybrid-sleep.target  
systemctl status sleep.target
```

## Sauce

<https://askubuntu.com/questions/1270147/ubuntu-20-04-keeps-goes-to-sleep>

[https://en-wiki.ikoula.com/en/Disable\\_Ubuntu\\_sleep\\_mode](https://en-wiki.ikoula.com/en/Disable_Ubuntu_sleep_mode)

<https://www.tecmint.com/disable-suspend-and-hibernation-in-linux/>

---

ubuntu kubuntu sleep fuckery xubuntu xkubuntu xsleep xfuckery